

Version 8.2 released 14 January 2012

- There are now **two (!)** executable files, '**lekseecon.exe**' for use with SIOC variables and '**lekseecon_f.exe**' for use with FSUIPC offsets. The FSUIPC_MODE parameter in lekseecon.ini is no longer needed and has been removed.
- The **lekseecon.ini** and **lekseecon_f.ini** files have to be placed in your **My Documents** folder instead of the lekseecon folder. The advantage is that we no longer have to write in the lekseecon folder, so lekseecon can be installed in C:\Program Files (x86)\lekseecon without any problems. This is more in line with the Microsoft Policy of users not writing in C:\Program Files area.
- It is **no longer** possible to use a **logical computer name** instead of an **IP-address** as value for the HOSTADDRESS parameter. There were errors in the implementation. This only affects users running SIOC at another PC than lekseecon.
- The file '**rotswitches.ini**' is no longer used; rotary switch position at start-up information can be put in the file lekseecon.ini.
- The name of the log file has changed from lekseecon_log.txt to '**lekseecon.log**'; the log file for lekseecon_f.exe is '**lekseecon_f.log**'.
- **Logging messages** between SDK and cockpit (LOG_TO_LEVELD, LOG_TO_COCKPIT and LOG_FROM_COCKPIT) has been **removed**. I try to keep the executable as small as possible.
- The **Decision Height algorithm** has been **improved**, the value set will be reached much faster!
- The **lekseecon variables** that you want to use in lekseecon_f.exe (when using **FSUIPC**), can be put **directly in lekseecon_f.ini**. There is no longer need for a CONFIG_FILE parameter and a separate configuration file for that purpose.
- Two new error messages (32 and 33) report **corrupt sioc.ini files** and a new SIOC error message (37) reports that your CONFIG_FILE file parameter has **no .ssi extension**; other SIOC error messages renumbered.
- A **new FSUIPC error message 51** about not finding lekseecon_f.ini was added; FSUIPC error message 41 renumbered to 52.
- The file '**setup_readme.txt**' with installation instructions was added to the setup_lekseecon installer archive, in case people have not read the installation instructions in the Manual.
- The **installer** program has been improved: it will now take the **installation folder** of your **previous** installation (if any) as suggested installation folder; it will detect if **uninstallation** of a previous version **failed** and show a pop up message with instructions what to do; and it will give you **four installation options**.
- Manual re-organised in order to make a more clear distinction between SIOC and FSUIPC usage; added more installation instructions.
- ... and, again, a lot of implementation improvements under the Hood.